MANURE UTILIZATION GUIDELINES



Published by:

Maine Department of Agriculture Conservation and Forestry

State House Station # 28 Augusta, Maine 04333

These Guidelines were reviewed by the following Agencies and Organizations:

Farm Service Agency UME Cooperative Extension - Androscoggin & Sagadahoc Counties UME Cooperative Extension - Aroostook County **UME Cooperative Extension - Aroostook County** UME Cooperative Extension - Aroostook County **UME Cooperative Extension - Cumberland County** UME Cooperative Extension - Franklin County UME Cooperative Extension - Hancock County UME Cooperative Extension - Kennebec County UME Cooperative Extension - Knox & Lincoln Counties **UME Cooperative Extension - Oxford County** UME Cooperative Extension - Penobscot County UME Cooperative Extension - Piscataguis County UME Cooperative Extension - Somerset County UME Cooperative Extension - Waldo County UME Cooperative Extension - Washington County UME Cooperative Extension - York County **UME Cooperative Extension Main Office** Agricultural Council of Maine (AGCOM) Maine Agricultural and Forest Experiment Station Maine Audubon Society Maine Municipal Association Maine Poultry Federation Maine Conservation District Advisory Council Maine Association of Conservation Districts Maine State Grange Natural Resources Council of Maine Soil Conservation Society of America, Pine Tree Chapter Maine Farm Bureau Natural Resources Conservation Services Department of Environmental Protection Maine Forest Services Maine Land Use Regulation Commission State Planning Office Aquaculture Association of Maine Beef Industry Council of Maine Beef Producer's Association of Maine Brown Egg Council of New England **Dairy Industry Association** Deer & Elk Farmer's Association of Maine Deer Farmers, Northern New England Equine Industry Association Hog Grower's Association Maine Horse Association

Maine Organic Farmers and Gardeners Association
Maine Sheep Breeders Association
Maine Department of Marine Resources
Maine Horse Association

Table of Content

Nutrient Man	agement Plan	
Standards		3
1. Calcu	late Crop Nutrient Needs	3
a.	Determine the nutrient content of your manure	3
b.	Soil test each field	
c.	Determine the Nutrient requirements of the crop	4
	Use the N and P Priority Matrix	
e.	Use manure as your primary source of plant nutrients	4
2. Manu	re Utilization	4
a.	Transportation method	4
b.		
c.	Time applications based on crop need	4
d.	Use correct application technique	4
e.	Buffers (setbacks)	5
3. Genera	l Manure Field Stacking Guidelines	5
a.		5
b.	General Recommendations	5
c.	Siting Recommendations	6
Attachm	ent 1: NMP requirements	7
Attachm	ent 2: Manure sample information form	8
Attachm	ent 3: How to take a soil sample	9
	ent 4: Residual Nitrogen Contributions	
	ent 5: Calculating Total Pounds of N and P ₂ O ₅ required for	
	Crop Growth	11
Attachm	ent 6: N and P Manure Priority Matrix	
	ent 7: Manure Application Guide	
	11	

MANURE UTILIZATION GUIDELINES

These Guidelines replace The Maine Guidelines for Manure and Manure Sludge Disposal on Land, July 1972, published by the Life Sciences and Agriculture Experiment Station, University of Maine Cooperative Extension Service and the Maine Soil and Water Conservation Commission.

NUTRIENT MANAGEMENT PLAN

Maine law and Chapter 565, the Nutrient Management Rules, requires that many farms have and follow a Nutrient Management Plan, developed by or approved by a Certified Nutrient Management Planning Specialist, certified by the Commissioner of the Department in accordance with 7 MRSA Chapter 747 (see attachment 1 for farms required to have a Nutrient Management Plan).

For farms that are not required to have a Nutrient Management Plan and for those farms which have not chosen to voluntarily develop one, the following guidelines may be followed for storage and utilization of manure.

STANDARDS (Nutrient Management Plan not required)

1. CALCULATE CROP NUTRIENT NEEDS - The following should be considered when determining crop nutrient needs. Crop nutrient needs should be determined for each field and for each crop type:

- a. Determine the nutrient content of your manure This should be done by sampling your manure and having it analyzed for N, NH₃-N, P₂O₅, K₂O+H₂O. If you have more than one type of manure or storage method (liquid vs. field stacked), take samples from each storage area. You should also take into consideration N losses through volatilization, depending upon application method (up to 80% of ammonia N is available to the crop if incorporated within 2 days but only about 20% is available if not incorporated or incorporated after 7 days). Sampling should be done at least every 5 years or when there is a management change that affects manure nutrient values. It is critical that the sample be taken and handled properly, or you will get an inaccurate reading. (See attachment 2 for manure sampling and handling procedure).
- b. Soil test each field- Each field should be soil tested at least once every 5 years to determine P, K, Mg, Ca and pH levels. N levels in the soil are not measured in the standard soil test because N is so mobile in some forms that the levels constantly change. For corn, you can do a soil N test for a crop that is in the early stages of growth, but it is difficult to apply manure at that time. N needs are generally based upon the crop needs but residual N from legumes and previous manure applications should be taken into consideration (see attachment 4 for calculating residual nitrogen contributions from legumes). If a field has a significant change in soil type, drainage

- or management practice, samples should be taken from each of the different areas in the field. Follow "Instructions on how to take a soil sample" by the University of Maine Plant and Soil Lab" (see attachment 3).
- c. Determine the nutrient requirements for the crop- Crop nutrient requirement should be based upon realistic yield goals for your specific soil types and cropping practices. Realistic yield goals for most major crops are listed on attachment 5. You can use actual yield goals that are in excess of those listed on the attached table if you can demonstrate that in 2 out of 5 years your average exceeded these thresholds. Application method and incorporation times must also be considered.
- **d.** Use the N and P Priority Matrix To determine which nutrient to base manure application rates on, use attachment 6, N and P Priority Matrix. Supplement with other nutrient sources once the appropriate threshold has been exceeded.
- e. Use manure as your primary source of plant nutrients Manure should be your primary source of nutrients for growing a crop. Other nutrient sources should only be used as a supplement to provide nutrients not supplied by the manure.
- **2. MANURE UTILIZATION** The following should be considered when utilizing manure on the farm as a soil amendment or nutrient:
 - **a.** Transportation method Choose a method to transport your manure that is appropriate for the type (consistency) of manure. It should not result in leakage or spillage that can become a nuisance or source of pollution.
 - **b.** Calibrate application equipment The equipment you use for spreading manure should be based upon the type of manure (consistency) you intend to spread. Regardless of the application equipment you use, it will need to be calibrated so that you only apply the nutrients needed to produce the desired crop. The equipment should be checked periodically (at least annually) to verify that the proper application rate is being applied. (See attachment 7, which is a chart for calculating manure spreading rate).
 - c. Time applications based on crop need To maximize nutrient uptake by a crop, the nutrients should be applied so that they are available when the crop needs them. Manure applied at times other than when the crop needs them should utilize techniques to maximize nutrient retention and availability for the crop to use when it is growing (as an example, grow a cover crop to uptake nutrients in the fall so they will be available to the crop the next spring when the cover crop is plowed down). Do not spread on frozen or snow-covered ground.
 - **d.** Use correct application technique Start in the corner of the field furthest from the entry point so that you don't have to drive through it repeatedly before driving on a public road. Make sure spreader is spreading evenly. Do not overlap spreading patterns or turn around in the same area repeatedly while still spreading.
 - **e. Buffers** (**setbacks**) Use setbacks to create buffers to protect water quality. Buffer widths should be determined on a site-specific basis taking into consideration such factors as field slope, soil type, drainage, watershed size, row direction, cover crop, tillage method, sensitivity of water body, type of well, season manure is applied and

rate of manure application. In lieu of site-specific buffer widths, the following can serve as setback guidelines:

- 1. 25 feet from intermittent and perennial streams and rivers
- 2. 100 feet from lakes, ponds and marine water bodies
- 3. 100 feet from private wells and springs
- 4. 300 feet from public wells¹
- 5. 35 feet from diversions, drainage ditches, gullies, non-vegetated swales and ravines
- 6. 25 feet from property lines
- 7. Avoid bedrock outcrops

3. GENERAL MANURE FIELD STACKING GUIDELINES - The Maine Department of Agriculture, Conservation & Forestry requires that Manure Field Stacking Sites be located by qualified professionals when they are part of a Nutrient Management Plan. If a Nutrient Management Plan is not required and has therefore not been developed, the Department recommends the following guidelines:

a. Applicability:

These guidelines have been developed to be used by persons with no field training or practical experience in the location and/or development of manure field stacking sites. They should be used only for farms with stackable manure (18% dry matter or greater). The setback numbers recommended in these guidelines are conservative because they are general in nature and do not take into consideration site specific conditions. If you wish to use site specific setbacks, they should be determined by a qualified professional (a person who has been trained and is experienced in developing site-specific field stacking plans).

b. General Recommendations:

- 1. Locate as many suitable field stacking sites as possible. This will allow for rotating between field stacking sites and/or stacking smaller amounts of manure in several locations as compared to larger amounts in fewer locations.
- 2. Unless otherwise necessary, only stack that amount of manure in a field that is needed to meet the fields nutrient requirements.
- 3. Only stack more manure in a field than is needed to meet the field's nutrient requirements when suitable stacking sites are not available on surrounding fields or when unable to access other field stacking sites due to weather, road or soil conditions.

c. Siting recommendations:

- 1. Choose a site which is on a knoll or high position in the landscape so that the soil does not have a high water table and does not receive much runoff. Sites which are mostly low and wet with only small knolls should be avoided or they should be evaluated by a qualified professional.
- 2. Do not stack manure on a site with less than 24 inches of soil between bedrock and the bottom of the manure pile. It may be possible to modify shallower soils but will

¹ Mandatory for people required to develop a Nutrient Management Plan.

- require the assistance of a qualified professional.
- 3. Do not stack manure on sites where the soil is gravel or sand. It may be possible to modify such soils so that they can be stacked upon but will require the assistance of a qualified professional.
- 4. The stacking site should be on as level a slope as possible but should not be on a slope greater than 5%. With the assistance of a qualified professional, it may be possible to modify a site with greater than a 5% slope so that it can be stacked upon.
- 5. The stacking site should meet the following setbacks unless site specific set-backs have been developed by a qualified professional:

<u>FEATURE</u>	SETBACK D WHEN FEA	
	upslope	downslope
Perennial (year-round) Waterbodies	100'	300'
Intermittent (seasonal) Waterbodies	50'	200'
Private Water Supplies (not owners)	100	300'
Public Water Supplies (wells, lakes, ponds, rivers, springs)	300'	300'
Private Water Supplies (owners)	100'	200'
Property Line	100'	200'
Residences (neighbor)	300'	300'
Diversion	25'	150'
Gully/Swale/Ravine	25'	150'
One Hundred Year Flood Plain	Not Within	Not Within

If you cannot locate a manure field stacking site which falls within all these guidelines, you should contact a qualified professional. A qualified professional will take into consideration site specific conditions to identify and/or develop field stacking sites for your manure. They are also trained to modify existing site conditions, when necessary, to develop manure stacking sites in fields which would not otherwise have suitable sites. For a list of qualified professionals contact:

Maine Department of Agriculture, Conservation & Forestry Division of Animal & Plant Health Nutrient Management Program State House Station # 28 Augusta, Maine 04333 Phone (207) 287-7608

(From Nutrient Management Rules Chapter 565)

§1. §4. Nutrient Management Plans Required.

Unless exempted by statute or these rules, a person who owns or operates a farm shall have and implement an approved nutrient management plan for that farm if it meets one or more of the following criteria:

- A. The farm confines and feeds 50 or more animal units at any one time;²
- B. The farm stores or utilizes more than 100 tons of solid manure or 25,000 gallons of liquid cow manure or compost per year not generated on that farm;
- C. The farm is the subject of a verified complaint of improper manure handling³;
- D. The farm stores or utilizes regulated residuals.

The nutrient management plan must be prepared and signed by a certified NMP specialist or approved and signed by a certified NMP specialist, pursuant to the provisions of §7 of these rules.

²Note: This means that the farm confines and feeds any combination of animals totaling 50,000

lb. live animal weight. Without limitation, some examples are:

²⁴ dairy cows (plus an equivalent number of young cattle) (1400 lb./mature animal)

³⁵ dairy cows with no young cattle (1400 lb./animal)

⁵⁰ beef cows (1000 lb./animal)

¹²⁵ sows or finishing pigs (400 lb./animal)

¹⁰⁰⁰ feeder pigs (50 lb./animal)

⁵⁰ horses (1000 lb./animal)

⁵⁰⁰ sheep (100 lb./animal)

²⁸⁰⁰ turkeys (18 lb./animal)

^{10,000} laying hens/broilers (5 lb./animal).

³Note: Complaints usually are handled under the 'Maine Agriculture Protection Act, 7 MRS Chapter 6 §151 et seq.

MANURE SAMPLE INFORMATION FORM Name: Mailing address: Voice no. Would you like your report faxed? State If so ,fax no. Sample name: Date Sample: Analysis includes: percent moisture, total nitrogen, ammonia nitrogen, total phosphate and total potash. Include a check payable to "Analytical lab", to cover the \$25 analysis fee for each sample. Results should be mailed back in are to two weeks time. Check those items which best describe your situation: KIND OF MANURE: MATERIAL WILL BE HANDLED AS: Dairy Beef Solid (results reported per ton) Swine Poultry Liquid (reported per 1000 gal.) Horse Sheep Other (List) Sampling Instructions 1) Timing: it is best to sample your manure at least one month before spreading. This allows time for lab turnaround and the development of a manure management program for your fields based on the results. 2) A PVC tube sampler is a handy device for sampling both semi-solid and liquid samples. Check with your local Extension or NRCS office. They may have one that you can borrow. If not, use a shovel or bucket, 3) Scrape any frozen or dried crust from the outside of the storage or pile. Agitate and throughly mix liquid storages before sampling. 4) The sample should be representative of the entire storage. Taking 3 to 4 subsamples uniformly distributed around the entire storage should be sufficient. Sample the entire depth profile of the storage if possible. 5) Solid/semi-sold samples: take 3 to 4 subsamples with a shovel or inner pipe only of the tube sampler. Be sure to include both manure and bedding in the sample. Place all subsamples in a clean bucket. 6) Liquid samples: take 3 to 4 subsamples with the sampling tube by inserting it vertically into the storage. Insert it with the holes covered, turn the inner tube to line up the slots and take the sample, turn it back to cover the slots and withdraw the tube. Empty the tube with the plug in the bottom into a clean bucket. Use a small bucket to sample liquid if no tube is available. 7) Thoroughly mix all subsamples in the bucket and fill a quart or pint mason jar. Leave at least one inch headspace in the jar and seal with an airtight screw-on lid. The headspace is critical to allow for expansion when the sample is frozen. 8) Keep the sample(s) cool until you can make arrangements for delivery to the lab. If you can't deliver the sample(s) to the lab on the same day, it is best to freeze it to prevent fermentation. It is possible to ship samples by UPS or Priority Mail if frozen and well insulated with newspaper. Ship early in the week. It may be possible to drop your sample(s) off at your local Extension or NRCS office for delivery to the lab. Check with them ahead of time to make arrangements. Please mail form and sample(s) to: Analytical Lab 5722 Deering Hall Orono ME 04469-5722

INSTRUCTIONS ON HOW TO TAKE A SOIL SAMPLE:

Soil is quite variable over a surprisingly small area. The following steps will help you get a soil sample that truly represents the area you want tested.

1 FORMS

Obtain information and sample boxes from the County Extension office. This form should be filled out as completely as possible. Sample forms may also be download & printed from our web site: http://anlab.umescl.maine.edu

2 EQUIPMENT

A soil sample can be taken with a probe, spade garden trowel, or soil auger.


3 DEPTH

Areas to be planted to row crops or seeded down should be sampled to plow depth (or about 8 inches.) Areas in sod, such as lawns or a syfields, should be sampled to a 3-or 4-inch depth. Areas under tree crops should be sampled to a 12-inch depth.

4 AREAS OF SAMPLING


Low spots, trouble spots, and areas with obvious differences in soil type should be treated as separate sampling areas. Also, areas that have been treated differently in the past should be sampled separately. In areas where past treatments and soil types are uniform, limit the sampling area to 8 acres in size. Make a permanent field sampling map for your reference when test results are returned.

EXAMPLE 50 ACRE AREA



5 TAKE A REPRESENTATIVE SAMPLE

Take soil from approximately 15 different spots in the sample area. Place this soil in a clean plastic bucket and mix thoroughly.



6 HOW MUCH IS NEEDED?

Fill a half-pint container from this bucket of well-mixed soil. Maine Soil Testing Service sample boxes are preferred. Your local Cooperative Extension office has soil test boxes.

7 LABEL THE CARTONS

The carton from each sample area should be identified on the side with the identification of the sample area and your last name. DO NOT put identification on top, because covers are thrown away. Be sure identifying names agree with your map of sample areas, so when test results are returned there will be no question of where the samples were taken. Be sure the names on the cartons agree with the names on the information form(s).

pH MANAGEMENT LEVELS

The typical pH management levels that are assumed to be optimum for field crops and for gardens and grounds in Maine are as follows:

general agronomic crops - 6.5

broccoli, cauliflower, or peas in potato rotation - 6.0

commercial potatoes & other potato rotation crops - 5.5

commercial beans and sweet corn - 6.0

all other commercial vegetables - 6.5

home gardens and organic crops - 6.5

blueberries, other acid-loving plants below 5.2

(current pH)

all other commercial fruit - 6.0

all turf - 6.0

all forestry - 6.0

shade trees - current pH

shrubs (other than azaleas & rhododendrons) - 6.0

all other ornamentals - 6.5

These are the "default" pH management levels. If for some reason you wish to manage your pH at some other level, please choose one of the alternative pH levels listed on page 1.

AVAILABLE ANALYTICAL SERVICES	(FER SAMPLE)
STANDARD SOIL TEST: Soil pH; available P, K, Ca, Mg; Organic Matter; Available Zn (field com and potatoes only); Lead Scan (gardens and grounds only); Exchangeable Na (on rerequest); Lime and fertilzier recommendations.	\$ 10.00
GREENHOUSE MEDIA TEST (for soilless potting mixes ONLY):pH; Available P, K, Ca, Mg, micronutrients; Soluble salts; Nitrate. (Use greenhouse sample form if possible)	\$ 10.00
Standard test plus soluble salts.	\$ 14.00
Standard test plus nitrates.	\$ 16.00
Soil micronutrient analysis and tissue testing are available on request. Contact the nearest cooperative extension office, or call: 581-2917 or 581-2945. Our current price list may also be viewed on our website: http://anlab.umesci.maine.edu.	

^{*} PRICES SUBJECT TO CHANGE .

RESIDUAL NITROGEN CONTRIBUTIONS FROM LEGUMES

Alfalfa:

First Year after Alfalfa

50% - 75% stand	110 lb./ ac.
25% - 49% stand	80 lb./ ac.
< 25% stand	40 lb./ ac.

Second Year after Alfalfa

50% - 75% stand 50 lb./ ac.

Red Clover and Trefoil:

First Year after Clover or Trefoil

> 50% stand	100 lb./ ac.
25% - 49% stand	70 lb./ ac.
< 25% stand	40 lb./ ac.

RESIDUAL NITROGEN FROM MANURE ORGANIC MATTER

When Applied	Percent of Total Organic N Availab							
	Poultry	Dairy or Other						
Current Year	60%	*25% - 35%						
1 Year Ago	10%	12%						
2 Years Ago	5%	5%						
3 Years Ago	5%	2%						

^{*}Use lower number for solid, higher number for liquid or slurry

AMMONIA-N LOSS TO VOLATILIZATION IF NOT INCORPORATED

Spring or summer applied

Days until Incorporation	Percent of Total Ammonia-N available										
	Poultry	Liquid Dairy	Solid Dairy								
0 - 2	80	55	60								
2 - 4	60	50	45								
4 - 7	40	45	25								
> 7	20	40	10								

Calculating Total Pounds of Nitrogen and P2O5 Required for Crop Growth:

The following tables should be used to calculate crop removal rates in Maine. Note the dry matter of the indicated yields. Producer yields need to be adjusted accordingly. Yield data must accompany any nutrient removal rates beyond the typical yield per acre listed.

Table 3. Typical Crop Nutrient Removal—Forage and Grain Crops

Crop (units)	lbs. Per	unit of yi	eld	Typical Yield/Acre	Removal for given yield (lbs/acre)						
	N	P_2O_5	K ₂ O		N	P ₂ O ₅	K ₂ O				
Corn (bu)	.75	0.4	0.3	120 (1)	00	50	2.5				
Corn silage(T) ¹	7.7	4.3	0.3 9.4	120 (bu)	90 155	50	35				
Forage Sorghum(T	(- 1) (- 1) (- 1)	3	10	20 (T)	135	86	188				
Sudangrass (T) ²	8	7	7	15 (T) 15 (T)	120	45	150				
Alfalfa (T) ^{3,4}	50	15	50	5 (T)	250	105 75	105 250				
Red Clover (T) 3.4	40	15	40	3.5 (T)	140	55	140				
Legume silage (T)		5	13.3	14 (T)	186	70	186				
Grass mixtures (T)		15	50	4 (T)	160	60	200				
Grass silage (T) 5.6	13.3	5	16.6	12(T)	160	60	200				
Wheat/rye (bu)7	1.5	1	1.8	60 (bu)	90	60	110				
Oats (bu) ⁷	1.1	0.9	1.5	80 (bu)	90	70	120				
Barley (bu) ⁷	1.4	0.6	1.5	75 (bu)	105	45	110				
Soybeans (bu) 3	3.8	1	1.4	40 (bu)	150	40	56				
Small grain sil. (T)	2 17	7	26	8.5 (T)	145	56	221				
Pasture ⁸					100	30	50				


Note: Adapted from Beegle, 1996 and Nutrient Recommendations for Field Crops in Vermont, 1998

- 1. 30% dry matter
- 2. 35% dry matter
- 3. Legumes can fix nitrogen. However, they are able to use nitrogen as indicated.
- 4. 90% dry matter or Hay equivalent (HE)
- 5. 30% dry matter
- 6. For grass/legume mixtures, use the predominant species in the mixture.
- 7. Includes straw
- 8. Yields are highly variable. Figures shown are for well managed pastures in rotation.

Typical Vegetable crop Removal Rates

For Vegetable crops removal rates and yields, consult the most recent version of the New England Vegetable Management Guide (available at your County Extension office)

N and **P** Manure Priority Matrix



Manure Application Guide

1. What is your manure application rate? From the chart below, select the (1) speader capacity, (2) spreader pattern length, and

Carond II		Par	COLLI	AAICI		ii rhi	oical m	Idill		hhii	Jano	115.				1	rate	hei	Acre =	Shi	cau	CI C	apa	City .	1 400	00,	1	2.500	I		a A LOI	igui	01 0	pice	iuj	
Spread	2000	gallon tank : 2500 gallon tank :							3000 gallon tank : 3500 gallon tank :								4000 gallon tank: 4500 gallon tank:																			
Width>	10'	15"	20'	25'	30'	35'	10'	15"	20'	25"	30'	35"	10'	15'	20'	30'	40"	50'	10'	15"	20'	30'	40'	50'	10'	15'	20'	30'	40'	50'	10'	15'	20'	30'	40'	50
Length						-					Li	quic	id manure application rate (1000's of gallons per aci										e)													
600'	151	101	71	61	51	4	181	12	91	7	6	5	22	15	11	7	5	4	25	17	13	8	6	5	29	19	15	10	7	6	33	22	16	11	8	7
800'	11	7	5	4	4	3	14	9	7	5	5	4	16	11	8	5	4	3	19	13	10	6	5	4	22	15	11	7	5	4	25	16	12	8	6	E
1000'	9	6	4	3	3	2	11	7	5	4	4	3	13	9	7	4	3	3	15	10	8	5	4	3	17	12	9	6	4	3	20	13	10	7	5	4
1200'	7	5	4	3	2	2	9	6	5	4	3	3	11	7	5	4	3	2	13	8	6	4	3	3	15	10	- 7	5	4	3	16	11	8	5	4	- 3
1400'	6	4	3	2	2	2	8	5	4	3	3	2	9	6	5	3	2	2	11	7	5	4	3	2	12	8	6	4	3	2	14	9	7	5	4	3
1600'	5	4	3	2	2	2	7	5	3	3	2	2	8	5	4	3	2	2	10	6	5	3	2	2	11	7	5	4	3	2	12	8	6	4	3	2
1800'	5	3	2	2	2	1	6	4	3	2	2	2	7	5	4	2	2	1	8	6	4	3	2	2	10	6	5	3	2	2	11	7	5	4	3	- 2
2000'	4	3	2	2	1	1	5	4	3	2	2	2	7	4	3	2	2	1	8	5	4	3	2	2	9	6	4	3	2	2	10	11.50	5	3	2	- 4
2500'	3	2	2	1	1	1	4	3	2	2	1	1	5	3	3	2	1	1	6	4	3	2	2	1	7	5	3	2	2	1	8	5	4	3	2	- 2
3000'	3	2	1	- 1	1	1	4	2	2	1	1	1	4	3	2	1	1	1	5	3	3	2	1	113	6	4	3	2	1	1	7	4	3	2	2	N.
Width> Length 600' 800' 1000' 1200' 1400' 1600' 1800' 2000' 2500'		24 18 15 12 10 9						27 20 16 13 11 10 9	20 15 12 10 9 7 7		40' 0's (0's (0's (0's (0's (0's (0's (0's		10 allons 44 33 26 22 19 16 15 13 10 9	29 22 17 15 12 11 10 9			11 8 7 5 5 4 4 4 3 3 3 3	9 7 5 4 4 3 3 3 2 2	22 16 13 11 9 8 7 7 7	15' 11 9 7 6 5 5 4 3						19 15 12 10 8	15 11 9	12	e (to	10 119 20	per ac 44 33 26 22 19 16 15 13	7e) 29 22 17 15 12 11 10 9	9 8 7 7 5	17	15 11 9 7 6 5 5 4 3 3	
3000'				-	-	- 1	0		14, 16	- 0	200			-	page ct.		-	-	(CO) 1-4011 (P.)	The same					OF THE	0.7		4	-	1100-6					_	
4.62	8 ton		ader	(230	bush	el)			ader	(290	bush	el)		- 31	ader	(350	bushe	el)	14 ton	spre	ader	(410	bush	el)	16 ton	spre	eader	(470	bush	nel)	18 tor	spre	ader	(530	bush	el)
Spread	8 ton	spre				3-17-17-17	10 ton	spre					12 ton	sprea		La transmission of the			14 ton	spre								(470		The Control	H	1000000	ader			
Spread Width>	8 ton	spre	ader			3-17-17-17	10 ton	spre			bush		12 ton	sprea	20'	25'	30'	35'	10'	15'	20'	25'	30'					Y. C. Carlon		The Control	H	1000000				
Spread Width> Length	10'	spre:	20'	25'		3-17-17-17	10 ton 10'	spre		25'	30'	35'	12 ton 10' Solid	sprea 15'	20'	25'	30'	35'		15' tons	20' pe	25' r ac	30' re)	35'		15		25'		The Control	10	15'				3
Spread Width> Length 600'	10°	spre:	20'	25'		35' 17	10 ton 10'	spre 15'	36		30'		12 ton	sprea 15' mar	20' ure	25' app 35	30' lica	35'	10' rate (15' tons	20' pe	25' r ac	30' re)	35'	10	15	58	25'		35	10	15'	20'	25'	30'	3
Spread Width> Length 600' 800'	10' 58 44	spre: 15' 39 29	20' 29 22	25' 23 17		35' 17 12	10 ton 10' 73 54	spre 15'	36 27	25' 29 22	30' 24 18	35' 21 16	12 ton 10' Solid 87	spre: 15' <i>mar</i> 58	20' ure 44 33	25' app 35 26	30' lica	35' tior 25	10' rate (15' tons	20' 5 pe 51 38	25' r ac. 41 30	30' re) 34 25	35' 29 22	116	15 77 58	58	25' 46 35	30' 39 29	35 ¹ 33 25	131	87 65	20' 65 49	52 39	30'	3
Spread Width> Length 600'	10°	spre: 15' 39 29 23	20' 29 22 17	25' 23 17		35' 17	10 ton 10'	spre 15' 48 36 29	36 27 22	25' 29 22 17	30' 24 18 15	35' 21 16	12 ton 10' Solid 87 65	spre: 15' mar 58 44 35	20' ure 44	25' app 35 26 21	30' lica 29 22	35' tior 25 19	10' rate (102 76	15' tons 68 51 41	20' 51 38 30	25' r ac. 41 30 24	30' re) 34 25	35' 29 22	116	15 77 58 46	58 44 35	25' 46 35 28	30' 39 29	35 33 25 20	131 98 78	87 65 52	65 49 39	52 39	30' 44 33	

1600' 1800' 2000' 2500'